





## STATES OF MATTER

- All forms of matter are made of particles: ATOMS, IONS, or MOLECULES
- This is referred to as : **THE PARTICULATE NATURE OF MATTER**
- Based on their physical properties, different forms of matter may be classified as:

	I. SOLIDS	II. FLUIDS	
At Room Temperature		1. Liquids	2. Gases
<b>PARTICLES</b>	 Ions	 Polar Molecules	 Non-polar Molecules
<b>SUBSTANCE</b>	$\text{Na}^+ \text{Cl}^-$ crystal	Liquid $\text{H}_2\text{O}$	$\text{O}_2$ gas
<b>COMPRESSIBILITY</b>	Incompressible	Incompressible	Compressible
<b>VOLUME</b>	Fixed volume	Fixed volume	Takes up all available volume
<b>SHAPE</b>	Fixed shape	Takes shape of container	Takes shape of container
<b>MOVEMENT OF PARTICLES</b>	No free movement (vibration only)	Very little Movement	Free movement
<b>FREE (EMPTY) SPACE</b>	Very little	Some free space	Mostly empty space
<b>FORCE OF ATTRACTION</b>	Very strong	Moderate	Negligible

## CHANGES OF STATE (PHASE TRANSITIONS)

**PHASE:** A homogeneous portion of a system      Examples:      Salt water, Air, Cooking oil




### VAPORPRESSURE

High energy liquid molecules from surface evaporate	More molecules of liquid escape into the vapor phase	Molecules of liquid still vaporize, but some vapor molecules return into liquid phase	Number of molecules which evaporate is the same as number of molecules which condense
Fast evaporation	Evaporation slows down	Rate of evaporation > Rate of condensation	Rate of evaporation = Rate of condensation
<ul style="list-style-type: none"> <li>• The vaporized molecules exert pressure in all directions</li> <li>• This pressure is called VAPOR PRESSURE</li> </ul>			$\text{H}_2\text{O (l)} \rightleftharpoons \text{H}_2\text{O (g)}$ <p style="text-align: center;"><b>DYNAMIC EQUILIBRIUM HAS BEEN REACHED</b></p>



## BOILING POINT

**NOTE:**

- As the temperature increases, the vapor pressure ( $p_v$ ) increases.

- When:

$$P_{\text{atm}} = P_v$$

↓  
**THE LIQUID BOILS**

Experimental evidence of boiling:

- Bubbles of water vapor form **WITHIN** the liquid water

- **BOILING POINT** is the temperature at which the vapor pressure of the liquid equals the atmospheric pressure

$$(P_{\text{atm}} = P_v)$$

- Consider the following situations:
  - Atmospheric Pressure = 1.00 atm
  - Boiling occurs when:  
Vapor Pressure = 1.00 atm
  - This requires a temperature of 100 °C
- Atmospheric pressure = 0.83 atm (High altitude)
  - Boiling occurs when:  
Vapor Pressure = 0.83 atm
  - This requires a temperature of 95 °C

**NORMAL BOILING POINT:** - the temperature at which the  $P_V = 1.00 \text{ atm}$   
**OR**  
 - the boiling point at 1.00 atmosphere of pressure

**CONCLUSION:**

- BOILING POINTS OF ALL LIQUIDS ARE TEMPERATURE DEPENDENT.
- The higher the atmospheric pressure, the higher the boiling point of the liquid

**For Water:**


At:	$P_{\text{atm}} = 1.00 \text{ atm}$	$P_{\text{atm}} < 1.00 \text{ atm}$	$P_{\text{atm}} > 1.00 \text{ atm}$
	$P_V = 1.00 \text{ atm}$	$P_V < 1.00 \text{ atm}$	$P_V > 1.00 \text{ atm}$
	B.P. = 100 °C	B.P. < 100 °C	B.P. > 100 °C
	Normal Boiling Point	At high altitudes or lowered pressure	

## MELTING POINT (M.P.) or FREEZING POINT(F.P.)

- F.P. - the temperature at which a pure liquid changes to a crystalline solid
- M.P. - the temperature at which a crystalline solid changes to a liquid

$$\text{F.P.} = \text{M.P.}$$

For water: F.P. = M.P. (at atmospheric pressure = 1.00 atm)



NOTE:

As long as the phases (solid water and liquid water) coexist, the temperature stays constant at  $0^{\circ}\text{C}$ .


- Melting or Freezing occurs at the temperature where the solid phase and the liquid phase are in dynamic equilibrium.



MELTING POINTS (OR FREEZING POINTS) OF SUBSTANCES:


- are independent of small variations in atmospheric pressure
- are affected by large pressure changes.

## HEATING CURVE FOR WATER



**NOTE:** There is no temperature change during phase transitions

Reason: During phase transitions, the energy absorbed is used to separate the molecules and not to speed them up



**Examples:**

1. Isopropyl alcohol ( $C_3H_7-OH$ ) on the skin cools by evaporation. How much heat is absorbed by isopropyl alcohol if 10.0 g evaporates? ( $\Delta H$  vaporization for isopropyl alcohol = 42.1 kJ/mol)

$$? \text{ kJ} = 10.0 \text{ g } C_3H_7-OH \times \frac{1 \text{ mole } C_3H_7-OH}{60.1 \text{ g } C_3H_7-OH} \times \frac{42.1 \text{ kJ}}{1 \text{ mole } C_3H_7-OH} = 7.00 \text{ kJ}$$

2. A 35.5 g sample of Cadmium metal was melted by an electric heater providing 4.66 J/s of heat. If it took 6.92 minutes from the time the metal began to melt until it was completely melted, what is the  $\Delta H_f$  (in kJ/mole) of Cadmium ?


$$? \text{ J} = (6.92 \text{ min}) \times (60 \text{ sec/min}) \times (4.66 \text{ J/s}) = 1935 \text{ J}$$

$$? \frac{\text{kJ}}{\text{mole}} = \frac{1935 \text{ J}}{35.5 \text{ g}} \times \frac{1 \text{ mole Cd}}{112.4 \text{ g Cd}} = 6.13 \text{ kJ/mole}$$

## PHASE DIAGRAMS

- Phase diagrams show graphical way to summarize the conditions under which the different physical states of a substance are stable.

### PHASE DIAGRAM FOR WATER



AB = M.P. curve at different pressures; Along AB :

solid  $\rightleftharpoons$  liquid

- AB leans slightly to the left (true for water only) Meaning: As the pressure increases, MP decreases slightly

AC = B.P. curve at different pressures; Along AC :


liquid  $\rightleftharpoons$  gas

- As the pressure increases, BP increases considerably (true for all liquids since Vapor Pressure  $\propto$  temperature)

AD = Vapor Pressure of solid (ice) at different temperatures

- Solid can sublime (solid  $\rightarrow$  gas) at  $p < 0.0060$  atm)

## PHASE DIAGRAM FOR WATER



A = Triple Point for Water;  $p_3 = 0.0060$  atm  $t_3 = 0.01^\circ\text{C}$   
 (4.58 mm Hg) (273.16 K)

= the p and the t at which SOLID, LIQUID, and GAS coexist


C = Critical Point for Water

$p_c$  = critical pressure = 218 atm  
 pressure above which the  
 substance can exist only as a liquid  
 at the critical temperature ( $374^\circ\text{C}$ )

$t_c$  = critical temperature =  $374^\circ\text{C}$   
 temperature above which the  
 substance can exist only as a gas

- Hot steam can be turned into liquid water by applying high pressure, as long as the temperature  $< 374^\circ\text{C}$
- Example: Critical temperature of Nitrogen gas =  $-147^\circ\text{C}$   
 To liquefy  $\text{N}_2$  gas, pressure must be applied at a  $t < -147^\circ\text{C}$

## PHASE DIAGRAM FOR CARBON DIOXIDE



AB = M.P. curve at different pressures; Along AB :

solid  $\rightleftharpoons$  liquid

- AB leans slightly to the right (general for all liquids)  
Meaning:  $\text{CO}_2$  can exist as a liquid only if  $p > 5.1$  atm

AC = B.P. curve at different pressures; Along AC :


liquid  $\rightleftharpoons$  gas

- As the pressure increases, BP increases considerably (true for all liquids since Vapor Pressure  $\propto$  temperature)

AD = Vapor Pressure of dry ice at different temperatures

- Dry ice can sublime (solid  $\rightarrow$  gas) at  $p < 5.1$  atm  
NOTE: At  $p = 1.00$  atm:  $\text{SOLID CO}_2 \rightarrow \text{GASEOUS CO}_2$  at any  $t > -78^{\circ}\text{C}$

## PHASE DIAGRAM FOR CARBON DIOXIDE



A = Triple Point for  $\text{CO}_2$  ;  $p_3 = 5.1$  atm  $t_3 = -57$  °C

= the p and the t at which SOLID, LIQUID, and GAS coexist

C = Critical Point for  $\text{CO}_2$

$p_c$  = critical pressure = 73 atm  
 = minimal pressure required at  
 31 °C to turn  $\text{CO}_2$  into a liquid

$t_c$  = critical temperature = 31 °C  
 = temperature above which  
 $\text{CO}_2$  cannot be turned into a liquid.